



Ejemplo: una cuerda de guitarra





$$T_{VA} = T \sin(\alpha) \approx T \frac{\Delta u}{\Delta x}$$

$$T_{VB} = T \frac{\Delta u}{\Delta x} + \frac{\partial}{\partial x} \left(T \frac{\partial u}{\partial x} \right) \Delta x$$

$$= T \frac{\Delta u}{\Delta x} + T \frac{\partial^2 u}{\partial x^2} \Delta x$$

$$T_R = T_{VB} - T_{VA}$$

$$T_R = \left(T \frac{\Delta u}{\Delta x} + T \frac{\partial^2 u}{\partial x^2} \Delta x \right) - T \frac{\Delta u}{\Delta x}$$


$$T_R = T \frac{\partial^2 u}{\partial x^2} \Delta x$$

$$T \frac{\partial^2 u}{\partial x^2} \Delta x = \rho \Delta s \frac{\partial^2 u}{\partial t^2}$$

$$\lim_{\Delta s \rightarrow 0} \Delta s = \Delta x$$

$$\frac{\partial^2 u}{\partial x^2} = \frac{\rho}{T} \frac{\partial^2 u}{\partial t^2} \quad c^2 = \frac{\rho}{T}$$

$$\boxed{\frac{\partial^2 u(x,t)}{\partial x^2} = c^2 \frac{\partial^2 u(x,t)}{\partial t^2}}$$



condiciones de frontera

$$\begin{cases} y(0, t) = 0 \\ y(l, t) = 0 \end{cases}$$

condición inicial

$$\begin{cases} y(x, 0) = \begin{cases} \frac{2a}{l}x & ; 0 \leq x \leq l/2 \\ 2a - \frac{2a}{l}x & ; l/2 \leq x \leq l \end{cases} \\ \frac{\partial y}{\partial t}(x, 0) = 0 \end{cases}$$

$$y(x, t) = \sum_{n=1}^{\infty} \left(\sin(n\pi x) \right) \left(b_n \cos(c n \pi t) + a_n \sin(c n \pi t) \right)$$

$$y(x, 0) = \sum_{n=1}^{\infty} \left(\sin(n\pi x) b_n \right)$$

$$F(x)_{\alpha=0} = C_1 x + C_2$$

$$CF \begin{cases} \psi(0, t) = 0 \\ \psi(1, t) = 0 \end{cases}$$

$$F(0) \Rightarrow C_1 \cdot (0) + C_2 = 0$$

$$F(1) \Rightarrow C_1 \cdot (1) = 0$$

$$\boxed{C_2 = 0}$$

$$\boxed{C_1 = 0}$$

$$F(x)_{\alpha=0} = 0$$

$$\text{Sol Pos } X = F(x) = C_1 e^{-\frac{\beta}{\epsilon} x} + C_2 e^{\frac{\beta}{\epsilon} x}$$

$$y(0, t) = 0 \quad F(0) = C_1(1) + C_2(1) = 0$$

$$\begin{aligned} F(x) &= C_1 e^{-\frac{\beta}{\epsilon} x} - C_1 e^{\frac{\beta}{\epsilon} x} \quad C_1 = -C_2 \\ &= \frac{C_1}{e^{\frac{\beta}{\epsilon} x}} - C_1 e^{\frac{\beta}{\epsilon} x} \end{aligned}$$

$$y(1, 0) \Rightarrow F(1) = \frac{C_1}{e^{\frac{\beta}{\epsilon}}} - C_1 e^{\frac{\beta}{\epsilon}} = 0$$

$$\boxed{\alpha > 0}$$

$$\frac{C_1}{e^{\frac{\beta}{\epsilon}}} = C_1 e^{\frac{\beta}{\epsilon}}$$

$$C_1 = C_1 (e^{\frac{\beta}{\epsilon}})^2$$

$$F(x)_{\alpha < 0} = C_1 \cos\left(\frac{\beta}{c}x\right) + C_2 \operatorname{sen}\left(\frac{\beta}{c}x\right)$$

$$F(0) = C_1 \cos(0) + C_2 (0) = 0 \quad \boxed{C_1 = 0}$$

$$F(x) = C_2 \operatorname{sen}\left(\frac{\beta}{c}x\right)$$

$$F(1) = C_2 \operatorname{sen}\left(\frac{\beta}{c}\right) = 0 \quad \text{si } \beta = c\eta\pi$$

$$\alpha = -c^2\eta^2\pi^2 \quad C_2 \neq 0$$

$$F(x) = C_2 \operatorname{sen}\left(\frac{c\eta\pi}{c}x\right)$$

$$g(t) = C_1 \operatorname{sen}\left(\frac{c\eta\pi}{c}t\right) + C_2 \cos\left(\frac{c\eta\pi}{c}t\right).$$